

Installing & Activating Node-Locked Licenses

Important Information -- read before you begin installing

- These instructions apply to Node-Locked licenses of ExtendSim Pro, DE, CP, and Analysis RunTime (ART).
- A Node-Locked license allows multiple users to use ExtendSim sequentially on one physical device.
- To install ExtendSim, activate the license, or launch ExtendSim, you may need to:
 - Run the Installer and/or launch ExtendSim as Administrator.
 - Temporarily disable anti-virus software or change settings in Windows Defender.
- For security, each end user can save the files they create in their own user accounts.
- If you have issues installing, activating, or launching ExtendSim, see the separate document *Frequently Asked Questions Individual & Node-Locked Licenses*.

Requirements

- Operating system: A 64-bit version of Windows, such as 11 or 10. *Note: The Node-Locked license does not run on virtual machines (VMs). If installing on a VM*, you must use a Floating license of ExtendSim.
- · Memory: 2GB RAM
- Disk space: 500 MB
- Subscription to the annual Maintenance and Support Plan (MSP). Not applicable to Analysis RunTime.

Installing and Launching ExtendSim

Installing

ExtendSim Node-Locked licenses have an automated software installer. Simply launch the installer file you downloaded by double-clicking it. Then follow the on-screen instructions to install ExtendSim.

- The ExtendSim application and other files that are not meant to be modified, such as the Help, will be installed by default in the folder *C:/Program Files/ExtendSim*.
- User-modifiable files (models & libraries), will be installed by default in the folder
 C:/Users/Public/Public Documents/ExtendSim. (If you move those files after installation, you must also change the ExtendSimDocPath.txt file located at Program Files/ExtendSim.)
- If you encounter issues while installing, see the document Frequently Asked Questions Individual & Node-Locked Licenses.

Note1: You may need to run the installer as Administrator.

Note2: The ART product installs RunTime versions of the ExtendSim libraries and does not install example models.




Launching

When you launch ExtendSim, an Activation Dialog appears. Activate your Node-Locked license using your Activation Key.

- The Activation Key represents your license for ExtendSim as well as which ExtendSim product you purchased.
- · See Activation instructions below.

If you get an error message when launching ExtendSim try running it as Administrator, or see the separate document Frequently Asked Questions • Individual & Node-Locked Licenses.



Activating the License

Automatic Activation -- requires internet access & security permission

- · Launch ExtendSim.
- In the Activation Dialog, enter your Activation Key and other required information. Click "Next".
 - If your device has internet access and its security system doesn't block the process, activation will occur automatically.
 - Otherwise you will have to activate manually, as described below.

Manual Activation -- if your device is not connected to the internet or its firewall or security system is blocking activation

- If ExtendSim is unable to accomplish activation automatically, it will present a message such as "Unable to Perform Automatic Activation".
- In the message, click the *Save Activation Info as Text File* button to generate a text file (*ExtendSim Activation Info.txt*) that contains the activation information.
 - You can save the text file anywhere you want; by default it is saved to the top level of the Public/Documents folder.
- Using an email address that can receive an attached text file in return, email the text file to Sales. Extend Sim@Andritz.com.
- We will generate a text file named extendsim.lic and email it to you. (Note: this may take up to 3 days to process.)
- Ouit ExtendSim.
- Place the extendsim.lic text file into the ExtendSim folder that contains the user-modifiable files (by default, C:/Users/Public/Public Documents/ExtendSim). (Don't place it in the Program Files/ExtendSim or the ExtendSim/Documentation folder!)
- Restart ExtendSim and you'll be activated!

Note: If your device is in a secure location, also see Secure Location Activation in the document Frequently Asked Questions • Individual & Node-Locked Licenses.

Once activated, the ExtendSim startup screen displays your Activation Key and Maintenance & Support Plan (MSP) renewal date.